VMWare DOS 共享文件设置方法

By Garbage

设置目的:

通过共享文件夹,你可以方便的在虚拟机和宿主机之间共享文件,减少重复代码输入的烦恼。

设置步骤:

1. 在虚拟机和宿主机之间启用共享时,确信 VMWare DOS 系统是停止的



2. 打开磁盘映射功能,步骤如图所示:



3. 关闭只读模式,选项如下图:

∎ap ¥irtual	Disk	×			
⊂ Virtual disk					
Select a virtual disk file and associated volume to map to a drive on your machine. When mapped, this drive is available in Windows Explorer.					
Eile name:	D:\VMware Workstation\MS-DOS\MS-DOS.vmdk Browse				
<u>V</u> olume:	Number Maximum Size 1 1023.7 MB				
(Open file in read-only mode (recommended)				
Map to					
<u>D</u> rive:	Z: 🔽 Open drive in Windows Explorer after mapping				
	OK Cancel Help				

4. 点击 OK,出现提示对话框,点击是。

∎ap Disk	File without Read-Only Protection		
1	You should only open a disk file in writable mode if you know for sure that no snapshots or clones are linked from the file.		
	This option should be used with extreme care.		
	If you make changes to a disk file that others are linked from, all those snapshots and clones will be invalidated and no longer usable.		
	Do you want to continue?		
	是① 否则		

5. 完成后,VMware 会自动打开映射后的磁盘。把需要的文件添加到里面即可。

文件(E) 编辑(E) 查看(V) 收藏(A) 工具(E) 帮助(B)							
③ 后退 ▼ ④ ▼ ⑦ 方退 ▼ ● 2件夹 □ ○ 2 ★ ○ 二 ○ ○ ○ ○ ○ ○ ○ ○ ○ ○ ○ ○ ○ ○ ○ ○ ○ ○							
地址 @ 😨 我的电脑							
名称 类型	文件 (2) 编辑 (2) 查看 (Y) 收藏 (A) 工具 (1) 帮助 (H)						
製造							
☞本地磁盘 (C:) 本地磁盘							
☞本地磁盘 0:) 本地磁盘		((1525 CT#0				
☞本地磁盘(E:) 本地磁盘	名称 🔺	犬小 奕型	修改日期				
☞本地磁盘 (F:) 本地磁盘	ABCD	文件夹	2010-7-21 14:24				
☞MSDOS710 (Z:) 本地磁盘	CESHI	文件夹	2010-7-20 16:38				
	CODE	文件夹	2010-6-28 13:29				
有可移动存储的设备	DOS	文件夹	2010-6-28 13:26				
	i 🗀 MASM	文件夹	2010-6-28 13:27				
🥝 DVD/CD-RW 驱 CD 驱动器	E TEMP	文件夹	2010-6-28 13:27				
②DVD 驱动器 (H:) CD 驱动器	T AUTOEXEC. BAT	1 KB Windows 批处理文件	2010-6-28 13:27	HSA			
	🖬 BOOTLOG. PRV	1 KB PRV 文件	2010-7-21 14:08	HA			
	📋 BOOTLOG. TXT	1 KB 文本文档	2010-7-21 14:27	HA			
	COMMAND. COM	93 KB 应用程序	2003-5-5 22:22	HSA			
	CONFIG. SYS	1 KB 系统文件	2010-6-28 13:27	HSA			
	DBLBUFF. SYS	3 KB 系统文件	1999-5-5 22:22	A			
	dblspace. Bin	68 KB BIN 文件	1999-5-5 22:22	RHSA			
	drvspace. Bin	68 KB BIN 文件	1999-5-5 22:22	RHSA			
	🖬 IFSHLP. SYS	4 KB 系统文件	1999-5-5 22:22	Å			
	🖬 IO. SYS	129 KB 系统文件	2003-11-28 16:35	RHSA			
	🖬 LOGO. SYS	127 KB 系统文件	2003-11-30 8:48	A			
	📷 MSDOS. SYS	1 KB 系统文件	2010-6-28 13:26	RHSA			

6. 拷贝完文件后,关闭磁盘映射功能。

Virtual	achine	Settings

Hardware Options				
Hardware Options	Summary 16 MB 1 1 GB Auto detect Auto detect Bridged Auto detect Auto detect Auto detect	Disk file MS-DOS.vmdk Capacity Current size: 9.6 MB System free: 719.6 MB Maximum size: 1 GB Disk information Disk space is not preallocated for this hard disk. Hard disk contents are stored in a single file. Utilities Adyanced Di sconnect Defr agnent Expand		
	Add	Expand Compact		
		OK Cancel Help		

×

7. 点击 Force Disconnect。



重新启动 VMware DOS 系统,开始调试旅程。